Region.clt

```
//  Element region file (client version)

version  6
1330501267

[region]                          Area
"□□□□□          "                    Area Name
1  895  0  5                      PK-Zone / Area ID / ? / Number of Points
-377.255249  138.131409  457.909088
-362.873779  78.828430  -221.574158
207.600723  58.555016  -202.462250
270.362122  174.479614  475.261200
-377.240601  138.131958  457.901886

[trans]                            Portal
1  16  1                          World ID To (e.g. Gaap) / World ID From (e.g. Pokari) / Minimum Level
-56.187237, 37.604233, -133.804794        Portal Co-ords From (e.g. Pokari)
2.500000, 25.000000, 2.500000            Portal Range Allowance
463.795013, 245.500000, 439.851013        Portal Co-ords To (e.g Gaap)


Credit: RougeAlma


[region]
"□□□     "
1 10
-2530.360596 212.984573 4179.893066
-2479.267334 220.548294 4190.765625
-2437.542236 220.995117 4137.787109
-2469.698486 218.411942 4087.776855
-2505.385742 221.888626 4047.897217
-2520.250244 217.868668 4051.548096
-2579.227051 217.949570 4079.913330
-2578.665527 216.452377 4123.163086
-2546.649414 218.257568 4170.906250
-2530.360596 212.984573 4179.893066

is the safezone section

the:
```

[trans]
116 1 0
-2392.144043, 260.299011, 4428.956055
10.000000, 5.000000, 5.000000
-175.348999, 256.104004, -437.670990

is the region transport

[trans] = tells it the following is transport info
131 1 60 = WORLD ID TAG TO / WORLD ID TAG FROM / LV REQ (IDK why HH/TT is 1 60; when every other [trans] is 1 0)
-2708.798096, 404.276001, 1185.218994 = this line tells it the cords to teleport from the map (in which this region file is for)
5.000000, 5.000000, 5.000000 = this I am guessing is the range for which the transport area works (how far outside of the above number)
-477.000000, 131.000000, 475.000000 = this line tells it where to take you inside the new location

Credit: 343

Revision #4
Created 2024-03-12 06:21:41 UTC by Arima
Updated 2024-08-12 17:09:27 UTC by Arima